

How to use HP-UX Network Node Manager (NNM) on a MS-Windows system without paying anything

Greg Baker (gregb@ifost.org.au)

November 30, 2007

1. Download and install Xming from <http://sourceforge.net/projects/xming>.
2. Download and install putty from <http://www.chiark.greenend.org.uk/~sgtatham/putty/>
3. Log in to the HP-UX system as root.
4. Edit `/etc/rc.config.d/xfst`. You will see a line `RUN_X_FONT_SERVER=0`.
Change that to `RUN_X_FONT_SERVER=1`
5. Run `/sbin/init.d/xfst start`
6. Back on your MS-Windows system, start a command prompt.
7. Type `"\Program Files\Xming\Xming" -fp tcp/hpuxserver:7000 -multiwindow`
8. Start Putty. Make sure that under the SSH tab, under the X11 tab, that you turn on "Enable X11 forwarding". It is off by default. You don't need to change any other defaults there.
9. Inside the putty session to the HP-UX system (as any user) run `ovw`.